


Upgrading Masternode to v2.1.3.2

SSH to your Linux server. Ubuntu 16.04 is recommended

First: Copy out your masternodeprivkey as it will be used back.
You can locate it by:

```
vi /root/.beetlecoin/beetlecoin.conf
```



```
root@beetlecoin: ~/beetlecoin
pcuser=user5410516
pcpassword=pass8733790
pcallowip=127.0.0.1
pcport=3134
isten=1
erver=1
aemon=1
ogtimestamps=1
asternode=1
ort=3133
asternodeaddr=
asternodeprivkey=5G
```

Make sure to run this command to stop daemon before you start
beetlecoin-cli stop

- 1.) **copy&paste:** wget <http://212.237.31.126/files/beet-mn.sh> -O beet-mn.sh
- 2.) **copy&paste** chmod +x beet-mn.sh
- 3.) **copy&paste** ./beet-mn.sh

Do you want to install all needed dependencies (no if you did it before)? [y/n]

N

Do you want to compile Daemon (please choose no if you did it before)? [y/n]

Y

Enter masternode private key for node , Re enter the Private Key save Previously

```

root@beetExplorerM:~/beetlecoin# chmod +x beet-mn.sh
root@beetExplorerM:~/beetlecoin# ./beet-mn.sh
Do you want to install all needed dependencies (no if you did it before)? [y/n]
n
Do you want to compile Daemon (please choose no if you did it before)? [y/n]
y
Stopping Daemon - Please Wait
--2019-05-13 06:07:15-- http://212.237.31.126/files/beetlecoind
Connecting to 212.237.31.126:80... connected.
HTTP request sent, awaiting response... 200 OK
Length: 7858856 (7.5M)
Saving to: '/usr/local/bin/beetlecoind'

/usr/local/bin/beet 100%[=====>] 7.49M --.-KB/s in 0.08s

2019-05-13 06:07:15 (97.3 MB/s) - '/usr/local/bin/beetlecoind' saved [7858856/7858856]

--2019-05-13 06:07:15-- http://212.237.31.126/files/beetlecoin-cli
Connecting to 212.237.31.126:80... connected.
HTTP request sent, awaiting response... 200 OK
Length: 383400 (374K)
Saving to: '/usr/local/bin/beetlecoin-cli'

/usr/local/bin/beet 100%[=====>] 374.41K --.-KB/s in 0.004s

2019-05-13 06:07:15 (89.9 MB/s) - '/usr/local/bin/beetlecoin-cli' saved [383400/383400]

Configuring IP - Please Wait.....
IP Done

Enter masternode private key for node , Go To your Windows Wallet Tools > Debug

```

After succesfully upgrade you will have same version as below.

beetlecoin-cli getinfo

```
root@beetExplorerM:~/beetlecoin# beetlecoin-cli getinfo
```

```
{
  "version": 2010302,
  "protocolversion": 70104,
  "blocks": -1,
  "timeoffset": 0,
  "connections": 0,
  "proxy": "",
  "difficulty": 1,
  "testnet": false,
  "status": "Blockchain information not yet available"
}
```